


Android Email Configuration


When you are configuring an email account, Linkeo's customer service can help you to recover your old emails stocked at IMAP. This page will show you the basic settings you need to send and receive emails. The Linkeo Business mail offers you a stock email of 3Go and a limit at sending and receiving emails of 20Mo. If you require some extra email stock, please feel free to contact us at **800 546 536 (800 - Linkeo)**. Mail : **service@linkeo.ae**.

This tutorial shows you how to set up your Android device to work with your e-mail account.

1 Open Email in the phone or tablet applications




2 Enter your e-mail address and password before pressing on Next



3. Choose the account type:

- a. Select **IMAP**.



Account setup

Account type

What type of account is this? Previous

POP3


IMAP

Exchange

4. Incoming server settings :

- a. Type your email address and you **User name**
Type your password
- b. Host Name:
If you are in **FRANCE**: fr.imap.linkeo.com
If you are in **AUSTRALIA**: au.imap.linkeo.com
If you are in **CANADA**: ca.imap.linkeo.com
If you are in the **UNITED STATES**: us.imap.linkeo.com
If you are in **DUBAI**: ae.imap.linkeo.com

Port: 143



Incoming server settings

Username
user@yourdomain.com

Password
.....

IMAP server
mail.yourdomain.com

Port
143

Security type

① . @ ABC DEF DEL
② 1 2 3


③ GHI JKL MNO
④ 4 5 6

⑤ 記号 PQRS TUV WXYZ
⑦ 7 8 9

⑧ 文字 A ⇄ a - , . 確定
⑨ あ A 1 0

5. Outgoing server settings :

- a. SMTP server:
 - If you are in **FRANCE**: fr.smtp.linkeo.com
 - If you are in **AUSTRALIA**: au.smtp.linkeo.com
 - If you are in **CANADA**: ca.smtp.linkeo.com
 - If you are in the **UNITED STATES**: us.smtp.linkeo.com
 - If you are in **DUBAI**: ae.imap.linkeo.com
- b. Security type: **STARTTLS(accept all certificates)**
- c. Port: **587**
- d. Make sure **Require sign-in** is selected.
- e. Enter the email address as **Username**.
- f. Enter the password.
- g. **Go next**




The screenshot shows a web interface for 'Account setup' with the following fields and options:

- SMTP server:** smtp.linkeo.com
- Security type:** STARTTLS (accept all certificates)
- Port:** 587
- Require sign-in.**
- Username:** [Redacted]
- Password:** [Redacted]

Navigation buttons: Previous, Next

6. Select the options you want in Account Options, and go Next



Account settings

Account options

Inbox checking frequency Every 15 minutes


Send email from this account by default.

Notify me when email arrives.

Sync email from this account.

Automatically download attachments when connected to Wi-Fi

7. You can setup a name for the account and enter a name you want to be displayed on outgoing message. Go Next, and finish the setup



Account setup

Your account is set up, and email is on its way!

Give this account a name (optional)

Your name (displayed on outgoing messages)
