


Android Email Configuration


When you are configuring an email account, Linkeo's customer service can help you to recover your old emails stocked at IMAP. This page will show you the basic settings you need to send and receive emails. The Linkeo Business mail offers you a stock email of 3Go and a limit at sending and receiving emails of 20Mo. If you require some extra email stock, please feel free to contact us at 1300 546 536.

This tutorial shows you how to set up your Android device to work with your e-mail account.

1. Open Email in the phone or tablet applications



2. Enter your e-mail address and password before pressing on Next



Account setup

Email account

You can set up email for most accounts in just a few steps.


Email address

Password

Manual setup Next

3. Choose the account type:

- a. Select **IMAP**.



The screenshot shows a web interface for account setup. At the top left, there is a small icon of an envelope with an '@' symbol and the text 'Account setup'. Below this, the heading 'Account type' is displayed. The main content area asks 'What type of account is this?' and provides three buttons: 'POP3', 'IMAP', and 'Exchange'. A 'Previous' button is located to the right of the question. The 'IMAP' button is highlighted, indicating it is the selected option.

4. Incoming server settings :

- a. Type your email address and your **User name**
Type your password
- b. Host Name:
If you are in **FRANCE**: fr.imap.linkeo.com
If you are in **AUSTRALIA**: au.imap.linkeo.com
If you are in **CANADA**: ca.imap.linkeo.com
If you are in the **UNITED STATES**: us.imap.linkeo.com
Port: 143



5. Outgoing server settings :

- a. SMTP server:
If you are in **FRANCE**: fr.smtp.linkeo.com
If you are in **AUSTRALIA**: au.smtp.linkeo.com
If you are in **CANADA**: ca.smtp.linkeo.com
If you are in the **UNITED STATES**: us.smtp.linkeo.com
- b. Security type: **STARTTLS(accept all certificates)**
- c. Port: **587**



- d. Make sure **Require sign-in** is selected.
- e. Enter the email address as **Username**.
- f. Enter the password.
- g. **Go next**

Account setup

Outgoing server settings

SMTP server:

Security type:

Port:

Require sign-in.


Username:

Password:

6. Select the options you want in Account Options, and go Next





 Account settings

Account options

Inbox checking frequency Every 15 minutes


Send email from this account by default.

Notify me when email arrives.

Sync email from this account.

Automatically download attachments when connected to Wi-Fi

7. You can setup a name for the account and enter a name you want to be displayed on outgoing message. Go Next, and finish the setup

 Account setup

Your account is set up, and email is on its way!

Give this account a name (optional)

Your name (displayed on outgoing messages)

